SSVE White Balance Data Visualization

20 Dec 2021, SSVE started a trial which is an activity to write White Balance data into Pmod T-Con board.

To ensure effectiveness, PE wanna check log data compared with JND.

This probject provides two solutions as follows:

Solution 01: VBA + Excel

Sample: N < 1,000

Toolkits:

1. using VBA for data wrangling;

2. using Excel for data visualization;

Usage: to confirm production samples or OQC samples.

demerits: Excel performance becomes poor when datasets are bigger than 1,000;

Solution 02: Python + Rlang

Sample: N > = 1,000

Toolkits:

```
1. using Python3 + Pandas for data wrangling
```

2. using Rlang + ggplot2 for data Visualization

(it is rather common in Data Scientist and industry)

Usage: to confirm enormous data samples (N > 100,000,000) from SSVE production to achieve peak performance.

Author

SSVE TVQA member @Zhang Liang, 20211220


Changelog

- v0.01, initial build
- v0.02, fix visualization bug (screw non-standard charts..)
- v0.03, resize named range dynamically
- v0.04, create Python3 + Rlang solution for scaling data and workload;
- v0.05, builder pipeline to dump all data into database

Diagram

the following the diagram of the whole process

SSVE White Balance Visualization @ZL, 20211221



Solution 01

toolkits: VB.NET + Excel + VBA;

using this approach when workload and dataset are small (<= 1,000);

Implementation

some core functionality as follows.

```
Private Sub read_PBM_csv(ByVal csv_path As String, ByRef dstWB As Workbook)
''' read data from a PBM csv log files at SSVE @ZL, 20211220
cool = Array(47, 58, 69, 80)
neutral = Array(107, 118, 129, 140)
warm = Array(167, 178, 189, 200)
expert1 = Array(227, 238, 249, 260)

color_temps = Array(cool, neutral, warm, expert1)

For i = lb To ub
```


```
dstRow = GetLastRow(dstWS_cool, dstCol_u) + 1
        dstWS_cool.Cells(dstRow, dstCol_ser).Value = dstWS_cool.Cells(dstRow,
dstCol_ser).Value & parse_pbm_fp(csv_path)
        dstWS_cool.Cells(dstRow, dstCol_u).Resize(1, 2) =
ConvXY to_uv(src_ws.Cells(cool(i), col_x), src_ws.Cells(cool(i), col_y))
' cool
        dstWS neutral.Cells(dstRow, dstCol ser).Value =
dstWS_neutral.Cells(dstRow, dstCol_ser).Value & parse_pbm_fp(csv_path)
        dstWS_neutral.Cells(dstRow, dstCol_u).Resize(1, 2) =
ConvXY_to_uv(src_ws.Cells(neutral(i), col_x), src_ws.Cells(neutral(i), col_y))
' neutral
        dstWS_warm.Cells(dstRow, dstCol_ser).Value = dstWS_warm.Cells(dstRow,
dstCol_ser).Value & parse_pbm_fp(csv_path)
        dstWS_warm.Cells(dstRow, dstCol_u).Resize(1, 2) =
ConvXY_to_uv(src_ws.Cells(warm(i), col_x), src_ws.Cells(warm(i), col_y))
' warm
        dstWS_expert1.Cells(dstRow, dstCol_ser).Value =
dstWS_expert1.Cells(dstRow, dstCol_ser).Value & parse_pbm_fp(csv_path)
        dstWS_expert1.Cells(dstRow, dstCol_u).Resize(1, 2) =
ConvXY_to_uv(src_ws.Cells(expert1(i), col_x), src_ws.Cells(expert1(i), col_y))
expert1
   Next i
   src_wb.Close False
   Set src_wb = Nothing
End Sub
```

Visualization


using some tricks to make dynamic charts.

Dynamic Chart

```
''' Dynamic Chart
' [ trick ]
' step1: using Formula -> Define Name to cusomize target series + offset()
function
' step2: using Click Chart -> select data series -> target series
' ref: https://support.microsoft.com/en-us/office/offset-function-c8de19ae-dd79-
4b9b-a14e-b4d906d11b66
' syntax: OFFSET(reference, rows, cols, [height], [width])
```



Gallary



Solution 02

toolkits: Python3 + Pandas + Rlang + ggplot2;

using this approach when workload and dataset are enormous (>=1,000);

Implementation

```
def main()->None:
    root:Path = './src'
    pfs = PBM_FileStruct()
    holder = Holder()
    offset:float = .0


pw = PBM_Wrangler(pfs, root, holder, offset)
    pw.work('./data/wb.db', 'wb')
```

Visualization

```
### plot
plot.wb <- function(df.temp, temp,</pre>
                     temp.breaks.x, temp.breaks.y,
                     temp.minor.x, temp.minor.y,
                     temp.jnd1, temp.jnd2, temp.jnd3) {
  p <- ggplot(df.temp) +</pre>
    geom_point(aes(x=u,
                   y=v),
               colour="purple",
               shape=21,
               fill='white',
               stroke=.5,
               alpha=.8,
               size=2) +
    # coord_cartesian(xlim=c(0.1771, 0.1991),
                        ylim=c(0.4247, 0.4467)) +
    scale x continuous(breaks = temp.breaks.x,
                        minor breaks = temp.minor.x) +
    scale_y_continuous(breaks = temp.breaks.y,
                        minor_breaks = temp.minor.y) +
    labs(title=gsub(' ', '', paste('WB::',
                                    temp,
                                     '(N=',
                                    length(df.temp$u),
                                     ')')),
         x="u\'",
         y="v\'") +
    annotate(geom='label',
             x=min(temp.jnd3$du)+0.002,
             y=max(temp.jnd3$dv)-0.002,
             label='0.010',
             colour='red',
             size=2) +
```

```
theme(plot.title = element_text(size=8),
        #panel.grid.major.x = element_blank(),
        #panel.grid.major.y = element_blank(),
        panel.grid.minor.x = element_blank(),
        panel.grid.minor.y = element_blank(),
        axis.title.x = element_text(size=8),
        axis.title.y = element_text(angle=0, size=8, vjust=0.5),
        axis.text.x = element_text(angle=90, size=5),
        axis.text.y = element_text(size=5)) +
  geom_path(data=temp.jnd1,
            aes(x=du,
                y=dv),
            size = 0.2,
            color = 'blue'
  ) +
  geom_path(data=temp.jnd2,
            aes(x=du,
                y=dv),
            size = 0.2,
            color = 'blue'
  ) +
  geom_path(data=temp.jnd3,
            aes(x=du,
                y=dv),
            size = 0.2,
            color = 'red'
  )
return(p)
```

Gallary



About

MIT License

Copyright (c) 2021 ZL

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND

NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.